



Plateia

by **CGS Labs**



Points Report Tutorial





CGS Labs d.o.o.

Brnčičeva ulica 13

1000 Ljubljana

Points Report

Copyright © 2021 CGS Labs d.o.o. All rights reserved.

Title: **Points Report**

Document date: 06. 12. 2021

Version: 1.0.

Printing: CGS Labs d.o.o.

T: +386 1 235 06 00

E: info@cgs-labs.com

Internet: www.cgs-labs.com

Table of Contents



INTRODUCTION	3
1. Report points to xls file	4
2. Report points to drawing	5
3. Creating a new table format	6

INTRODUCTION

In this tutorial, you will learn how to make a points report. As a user, you have two options. You can export the points report as an xls file or draw a table in the current drawing. Both options will be shown in this tutorial.

1. Report points to xls file


1. Click on the Points report icon.
2. Select CGS points in the drawing and press Enter.
3. The Points Report Table dialog box opens.
4. Click on this  button to export the points report to the xls file.
5. Specify the location of the file and confirm by pressing the Save button.
6. Then a new Excel file with the data of the selected points opens.



2. Report points to drawing

1. Click on the Points report icon.
2. Select CGS points in the drawing and press Enter.
3. The Points Report Table dialog box opens.

4. Click on the icon  and then specify the table insertion position.



X	Y	Z
429532.274721	91393.886013	593.378669
429526.915513	91396.057433	593.029844
429526.336138	91405.032621	592.584896
429525.611923	91413.573522	592.936058
429525.177395	91422.114429	593.167333
429525.202033	91430.735082	592.798291
429524.277928	91438.816415	592.407928

3. Creating a new table format

1. Click on the Points report icon.
2. Select CGS points in the drawing and press Enter.
3. Click on the Plus button. This opens a new dialog box.
4. Click in the Set data cell. The Set column data dialog box opens.
5. Select column data from the drop-down menu. If you want, you can also define a custom data name.
6. Click on the Set data again and define another column data. You can define as many columns as you want.

To edit the column simply click on the cell. It opens a dialog box, where you can change the column data and custom data name.

You can also delete a column. For this, you should first click on the column you want to delete. This opens a dialog box where you press OK and then click on the Delete column option.

7. When finished confirm by pressing OK.
- Then you can export to an xls file or drawing.

